



[Unity] Set Up MRTK2 For VIVE WAVE

Oct, 2023

This document contains information that is proprietary to HTC Corporation.

Unauthorized reproduction or disclosure of this information in whole or in part is strictly prohibited.

© 2023 HTC Corporation. All rights reserved.

Revision History

[illegible]

Contents

1.	Introduction	4
2.	Development Environment	5
2.1.	Download Packages	5
2.2.	Project Settings	6
2.3.	Fixed MRTK Shader	8
2.4.	Hand Interaction Example	9
2.5.	Eye Tracking Example	11
3.	Enable Passthrough	13
4.	Change Model	14
5.	Troubleshooting	15
6.	Appendix	16
6.1.	Single Scene With Eye Tracking	16

1. Introduction

VIVE Wave Unity plugin supports the **MRTK Support** feature. By following this guide you can build an application with MRTK and run on VIVE mobile devices.


The feature of **MRTK Support** :

- Controller
- Hand Tracking
- Eye Tracking


2. Development Environment

2.1. Download Packages


1. Download version 2.8.3 of MRTK Foundation, MRTK Tools and MRTK Examples (optional) from MRTK [GitHub](#).
2. Import these packages into your project and skip MRTK configurator setup.
3. Import WAVE SDK into your project from menu **Window > Package manager > Add package from tarball**.



4. Import MRTK Support feature from menu **Edit > Project Settings > Wave XR > XRSDK**.
5. Import MRTK2.8.3_VIVE package from Assets/Wave/XR/MRTKSupport/.




6. Check MRTK2 folder be added to Assets/ Wave/.




2.2. Project Settings


1. Switch to Android platform.
 2. Setup MRTK Configurator from menu **Mixed Reality > Toolkit > Utilities > Configure Project for MRTK**.
- 2.1. Select non-OpenXR if you wouldn't use OpenXR in your project.




- 2.2. Show Settings and enable Wave XR in XR Plug-in Management.




- 2.3. Apply and import the recommended settings.
3. Enable Natural Hand and Eye Tracking(optional) from menu **Edit > Project Settings > XR Plug-in Management > WaveXRSettings**.



4. Check WaveXRPlayerSettingsConfigDialog from menu **Edit > Project Settings > Wave XR.**
5. Disable multi-thread rendering and click ignore to avoid warning.



6. Check Graphics APIs from menu **Edit > Project Settings > Player > Other Settings** only select OpenGL ES3.



2.3. Fixed MRTK Shader


The MixedRealityStandard.shader from **Assets/MRTK/StandardAssets/Shaders/** may give an error in Unity 2022 LTS when building. Make these edits in the shader to fix this.

1. On line 775, fixed4 frag(v2f i, fixed facing : VFACE) : SV_Target change to fixed4 frag(v2f i) : SV_Target.
2. On lines 956 and 959, remove * facing.

2.4. Hand Interaction Example

You can build an example which imported by MRTK Examples to verify your environment.

1. Open demo scene HandInteractionExamples.unity from Assets/MRTK/Examples/Demos/HandTracking /Scenes/.
2. Change the MixedRealityToolkit Profile to ViveWave.MixedRealityToolkitConfigurationProfile.




3. Build and Run from menu **File > Build Settings**.
4. In the example, you can test the functionality of the controller, hand tracking, and eye tracking and also interact with UGUI and objects using hand ray or controller ray.

Controller : Trigger Press(Select), Grab Press(Grab)

Hand Tracking : Pinch(Select), Grab(Grab)

Note: Please refer to ViveWave.MixedRealityControllerMappingProfile from Assets/MRTK/Providers/Vive/Profiles/ for more input actions.


5. If you want to replace hand ray or controller ray to head gaze or eye gaze(it need to switch eye tracking profile), set controller type to nothing in ShellHandRayPointer of pointer options.




2.5. Eye Tracking Example

You can build an example which imported by MRTK Examples to verify your environment.


1. Open demo scene EyeTrackingDemo-00-RootScene.unity from Assets/MRTK/Examples/Demos/EyeTracking/ Scenes/.
2. Fix bug with offset by setting position of MixedRealityPlayspace to (0, 0, 0).




3. Change the MixedRealityToolkit Profile to ViveWave.MixedRealityToolkitConfigurationProfile. (Follow 2.4. Hand Interaction Example step 2)
4. Change the profile from **MixedRealityToolkit > Input > Pointers** to ViveWave.MixedRealityEyeGazePointerProfile



5. Open EyeTrackingDemo-(02~05) demo scene from Assets/MRTK/Examples/Demos/EyeTracking/ Scenes/
6. Disable EyeTrackingDemos ManagerComponents to avoid loading other profiles.




7. Add all demo scenes in Assets/MRTK/Examples/Demos/EyeTracking/Scenes/ to Scenes In Build from menu **File > Build Settings**.



8. In the example, you can use eye gaze and pinch gesture to switch scene and implement different interactive features.


3. Enable Passthrough

1. Import WAVE Native into your project from menu **Window > Package manager > Add package from tarball**.
2. Add script to call passthrough APIs, here listed the passthrough APIs:
public static WVR_Result WVR_ShowPassthroughUnderlay(bool show)
3. The clear flags of Opaque and Transparent in your camera profile should be set to Color or Solid Color and the background color should be set to (0, 0, 0, 0).



4. Change Model


1. Import WAVE Essence into your project from menu **Window > Package manager > Add package from tarball**.
2. Import Controller Model and Hand Model feature from menu **Edit > Project Settings > Wave XR > Essence** and ensure these prefabs are valid.
(Assets/Wave/Essence/Hand/Model/version/Resources/Prefabs/MRTK/)
(Assets/Wave/Essence/Controller/Model/version/Resources/Prefabs/MRTK/)
3. Ensure ViveWave.MixedRealityControllerVisualizationProfile from Assets/MRTK/Providers/Vive/Profiles/ is valid if not you should manually add new controller definition.



4. Change the Controller Visualization Settings from **Input System Profile > Controller** to ViveWave.MixedRealityControllerVisualizationProfile.

5. Troubleshooting

1. Hand tracking model not show.
⇒ Ensure that your Articulated Hand Tracking from **MixedRealityToolkit > Input** has added profile.



2. The direction of default controller model is warong.
⇒ Set Rotation Offset of ControllerLeft and ControllerRight from Assets/MRTK/SDK/StandardAssets/Controllers/ to (0, 180, 0).
⇒ Set the rotation of gameobjects named left/right under ControllerLeft/ ControllerRight to (0, 180, 0).
3. Input actions not working with hand or controller.
⇒ Ensure that controller input mapping settings from MixedRealityToolkit > Input > Controllers of articulated hand and vive focus are valid.

Articulated Left Hand Controller - Input Action Assignment	
Pointer Po:▼	Spatial Pointer
Grip Pose ▼	Spatial Grip
Select ▼	Select
Grip Press ▼	Grab
Index Fing▼	Index Finger Pose
Teleport D ▼	Teleport Pose


Vive Focus Right Hand Controller - Input Action Assignment	
Primary Bu▼	A Button Press
Primary Bu▼	A Button Touch
Secondary▼	B Button Press
Secondary▼	B Button Touch
ThumbStic▼	ThumbStick Axis
ThumbStic▼	ThumbStick Press
ThumbStic▼	ThumbStick Touch
Trigger ▼	Trigger Axis
Trigger Clc▼	Trigger Press
Select ▼	Select
Trigger Toi▼	Trigger Touch
Grip Press ▼	Grip Axis
Grip Press ▼	Grab
Grip Click ▼	Grip Press
Grip Touch▼	Grip Touch
Pointer Po:▼	Pointer Pose
Pointer Po:▼	Pointer Position
Pointer RoI▼	Pointer Rotation

6. Appendix

6.1. Single Scene With Eye Tracking

If you want to run one demo scene in MRTK Example, follow the steps below.

1. Open a demo scene (01~05) from Assets/MRTK/Examples/Demos/EyeTracking/Scenes.
2. Add MixedRealityToolkit, MixedRealityPlayspace and MixedRealitySceneContent from menu **Mixed Reality > Toolkit > Add to Scene and Configure** and delete MixedRealitySceneContent which doesn't contain any gameobjects.



3. Follow 2.5. Eye Tracking Example step 3~6.
4. Build and Run from menu **File > Build Settings**.